



Acer

Password



手指按住 Shift 按键 (不要放开), 然后滑鼠按 Power 和 Restart
不要放开 Shift 按键, 直到滑鼠按了 Restart, 才可以放开

Choose an option



Continue

Exit and continue to Windows 10



Troubleshoot

Reset your PC or see advanced options



Turn off your PC

⬅ Troubleshoot



Reset this PC

Lets you choose to keep or remove your personal files, and then reinstalls Windows.



Advanced options



⬅ Advanced options



System Restore

Use a restore point recorded on your PC to restore Windows



Command Prompt

Use the Command Prompt for advanced troubleshooting



System Image Recovery

Recover Windows using a specific system image file



Startup Settings

Change Windows startup behavior



Startup Repair

Fix problems that keep Windows from loading




Go back to the previous version

每一台电脑的位子可能不一样，
所以必须要确定看好好来，
一定要按 System Image Recovery




System Image Recovery


Recover Windows using a specific system image file




等一下，让电脑 scan 你的电脑




按 Cancel




按 Next



按 Advanced...



按 Install a driver




按 OK

进入这里时，必须要非常小心!!

**不可以按
Quick access**

**不可以按
Libraries**

**不可以按
This PC**



**为什么?
因为当你按出去
很难再找回来
System32**

**System32 就是
我们非常重要的
关键来破解密码**


进入这里时，必须要非常小心!!

进入这里时，必须要非常小心!!

不可以按
Quick access

不可以按
Libraries

不可以按
This PC




滑鼠在这里拉下来
找 Utilman

进入这里时，必须要非常小心!!

进入这里时，必须要非常小心!!

这就是我们要的
Utilman
我们要把它改名
变成 **Utilman1**

对，就只是加 1
在 **Utilman** 的后面
变成 **Utilman1**



滑鼠在这里拉下来
找 **Utilman**


进入这里时，必须要非常小心!!

进入这里时，必须要非常小心!!

滑鼠右键
按 Rename

把 Utilman 改名
成 Utilman1

对，就只是加 1
在 Utilman 的后面
变成 Utilman1




进入这里时，必须要非常小心!!

进入这里时，必须要非常小心!!

Utilman1

一定要改名成

Utilman1




进入这里时，必须要非常小心!!

进入这里时，必须要非常小心!!

虽然已经改了
Utilman1

但是它还是
Utilman

我们只需要
Refresh 一下
就可以了




找空白地方
滑鼠右键
然后按
Refresh

就可以了

进入这里时，必须要非常小心!!

进入这里时，必须要非常小心!!


**终于变成
Utilman1**



进入这里时，必须要非常小心!!

进入这里时，必须要非常小心!!

**接下来
我们拉上去
找 cmd**



**滑鼠拉上去
找 cmd**


进入这里时，必须要非常小心!!

进入这里时，必须要非常小心!!

**这就是
我们要的
cmd**

**在这里
我们把它
改名为**

Utilman




进入这里时，必须要非常小心!!

进入这里时，必须要非常小心!!

在 cmd
滑鼠右键
按 Rename

把它改成
Utilman
就可以了




进入这里时，必须要非常小心!!

进入这里时，必须要非常小心!!

**把 cmd 改成
Utilman
就可以了**


**接下来滑鼠
来这里空白
左键按一下**



**改好名字后
直接打叉
关掉所有东西**

进入这里时，必须要非常小心!!


进入这里时，必须要非常小心!!



按 Cancel

进入这里时，必须要非常小心!!

进入这里时，必须要非常小心!!



按打叉，关掉

进入这里时，必须要非常小心!!

Choose an option



Continue

Exit and continue to Windows 10



Troubleshoot

Reset your PC or see advanced options



Turn off your PC




Acer

Password



滑鼠按下这里



一个黑色的银幕跳出来


A screenshot of a Windows Command Prompt window. The title bar reads 'Command Prompt'. The window content shows the standard Windows boot sequence: 'Microsoft Windows [Version 10.0.16299.371]', '(c) 2017 Microsoft Corporation. All rights reserved.', and the command prompt 'C:\Users\Acer>'. The background of the window is black, and the text is white. The window has standard Windows window controls (minimize, maximize, close) in the top right corner.

```
Microsoft Windows [Version 10.0.16299.371]
(c) 2017 Microsoft Corporation. All rights reserved.

C:\Users\Acer>
```



在银幕里打字:
net user



```
Command Prompt
Microsoft Windows [Version 10.0.16299.371]
(c) 2017 Microsoft Corporation. All rights reserved.
C:\Users\Acer>net user
```

这就是你的
电脑名字



是不是 Acer

```
Command Prompt
Microsoft Windows [Version 10.0.16299.371]
(c) 2017 Microsoft Corporation. All rights reserved.

C:\Users\Acer>net user

User accounts for \.

-----
Administrator      DefaultAccount      DefaultAccount
Acer                WDAGUtilityAccount
The command completed successfully.

C:\Users\Acer>
```

```
Command Prompt
Microsoft Windows [Version 10.0.16299.371]
(c) 2017 Microsoft Corporation. All rights reserved.

C:\Users\Acer>net user

User accounts for \\

-----
Administrator      DefaultAccount      DefaultAccount
Acer                WDAGUtilityAccount
The command completed successfully.

C:\Users\Acer>net user Acer *
```

然后在里面打字

net user Acer *

注意: 打完 net user Acer, 后面一定要放 * (Shift + 8)


```
Command Prompt
Microsoft Windows [Version 10.0.16299.371]
(c) 2017 Microsoft Corporation. All rights reserved.

C:\Users\Acer>net user

User accounts for \\

-----
Administrator      DefaultAccount      DefaultAccount
Acer                WDAGUtilityAccount
The command completed successfully.

C:\Users\Acer>net user Acer *
Type a password for the user:
```

按 Enter 按键

注意: 在这里千万不可以放密码, 因为会造成电脑问题!!!
所以, 只能按 Enter, 不可以打任何字
否则, 我不能帮你了...



```
Command Prompt
Microsoft Windows [Version 10.0.16299.371]
(c) 2017 Microsoft Corporation. All rights reserved.

C:\Users\Acer>net user


User accounts for \\

-----
Administrator      DefaultAccount      DefaultAccount
Acer                WDAGUtilityAccount
The command completed successfully.

C:\Users\Acer>net user Acer *
Type a password for the user:
Retype the password to confirm: 
```

同样的，不可以打任何密码
只可以按 Enter
如果跑去打密码，以后老师没有办法帮你

好了后，直接按打叉关掉它



```
Command Prompt
Microsoft Windows [Version 10.0.16299.371]
(c) 2017 Microsoft Corporation. All rights reserved.

C:\Users\Acer>net user

User accounts for \.

-----
Administrator      DefaultAccount      DefaultAccount
Acer                WDAGUtilityAccount
The command completed successfully.

C:\Users\Acer>net user Acer *
Type a password for the user:
Retype the password to confirm:
The command completed successfully.
```

好了，搞定了



Acer

Password



滑鼠直接按箭头就可以了

